



LSI
Logistics
Software
International

**Logistics Solutions Provider
to
Supply Chain Management**



Mobility Solutions
ISV/Software Solutions
Business Process and Integration

Suite 9.2, Level 1
Zenith Business Centre
6 Reliance Drive
Tuggerah NSW 2259
Australia
Tel: +61 2 4351 3500
Email: support@lsi.net.au
Web site: www.lsi.net.au
ABN: 33 414 337 680

iSupply software application - release advice - version 8.6.1.1

Prerequisites - iSupply

iSupply version 8.5.1.1
Microsoft .NET Framework 4.0
Microsoft Report Viewer 2010 SP1
SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 8.6.1.1
Release status: General release
Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 8.6.1.1

released 22/10/2012 (018073)

MSI path and name:

<http://www.lsi.net.au/files/versions/iSupply-8-6-1-1.zip>

SQL update scripts:

DB8-6-1-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks
017935	PM	iSupplyPortal Launch new browser based portal for iSupplyWMS iSupply/iSupplyPortal
018004	SC	iSupply Stock Take-Up New Windows CE application to perform stock take-ups for single products in a bin location iSupplyRF [TD6]
018005	SC	Import Orders Add action types <Add> and <Cancel> to import XML iSupply
018073	LS	Consignment Details Enquiry Show correct receiver address in search list of consignments for returns iSupply/iSupplyWeb
018073	LS	Export Consignment Data to Transporter Print consignments in c/note number sequence on export report iSupply
018086	SM	Print Manifest Details Rectify program error when reprinting for a date range iSupply
018097	PM	Pick/Pack Rectify incorrect SSCC incrementing logic iSupply/iSupplyRF
Incorporations from fix versions		
From version 8.4.2.2		
018048	YM	Consignment Details Entry Rectify loss of dangerous goods data when in change mode iSupply
018076	YM	Export Sales Orders with Consignment Details Improve the data content of the consignment note number in the export file iSupply
From version 8.4.6.1		
018092	TA	Print Freight Labels Rectify non-printing of Toll Priority A4 freight labels to the laser printer iSupply

New maintainable settings

Setting	Details
---------	---------

User Accounts	Domain
User Accounts	Domain user name
User Accounts	Domain password
User Accounts	Reports root folder
Sender Details	Current order number
<u>Import/export file format changes</u>	
Transaction	Data fields
None	None

Notes

None

iSupply install steps for this release when upgrading from iSupply version 8.5.1.1

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 8-6-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 8-6-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 8-6-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 8-6-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 8-6-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 8-6-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 8-6-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 8-6-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB8-6-1-1.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.