



LSI
Logistics
Software
International

Logistics Solutions Provider
to
Supply Chain Management



Mobility Solutions
ISV/Software Solutions
Business Process and Integration

Suite 9.2, Level 1
Zenith Business Centre
6 Reliance Drive
Tuggerah NSW 2259
Australia
Tel: +61 2 4351 3500
Email: support@lsi.net.au
Web site: www.lsi.net.au
ABN: 33 414 337 680

iSupply software application - release advice - version 7.41.9.1

Prerequisites - iSupply

iSupply version 7.41.8.2
Microsoft .NET Framework 4.0
Microsoft Report Viewer 2010 SP1
SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 7.41.9.1
Release status: General release
Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 7.41.9.1 released 06/07/2010 (016852)

MSI path and name: <http://www.lsi.net.au/files/versions/iSupply-7-41-9-1.zip>

SQL update scripts: DB7-41-9-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks
014537	DH	Scheduled tasks - performance improvements
016874	DH	Export consignment note details - adjust contents of freight costs data fields
016878	LS	Import freight tracking details - rectify incorrect rejection of AaE and Star Track freight tracking import files

New maintainable settings

Setting	Details
None	None

Import/export file format changes

Transaction	Data fields
None	None

Notes

eCS configuration

=====

There are new configuration file entries that affect the manner in which eCS executes.

Configuration file "ConsignorVB.exe.config"

```
<add key="eCSMachineName" value="ServerName"/>
```

"ServerName" is the name of the server where the eCS service is installed and executes.

```
<add key="eCSServiceName" value="LSI eCommerce Control System"/>
```

This is a mandatory entry.

Configuration file "eCSService.exe.config"

```
<add key="INTERFACELOADINTERVAL" value="nnnn"/>
```

"nnnn" is the interval in seconds that scheduled task settings (as specified in Setup Scheduled Tasks) are refreshed in memory. The default value (if this line is not present) is 300 seconds.

```
<add key="ECSSETTINGSLOADINTERVAL" value="nnnn"/>
```

"nnnn" is the interval in seconds that eCS settings (as specified in System Setup) are refreshed in memory. The default value (if this line is not present) is 600 seconds.

```
<add key="INTERVAL" value="nnnn"/>
```

"nnnn" is the interval in milliseconds that the eCS service timer starts the process that determines the next scheduled task to execute. The default value (if this line is not present) is 1000 milliseconds.

Create/Modify User Accounts

=====

Security Settings - new checkbox "Allow eCS stop".

Setup Scheduled Tasks

=====

New data field "Max execution time".

New checkbox "Unschedule".

iSupply install steps for this release when upgrading from iSupply version 7.41.8.2

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-41-9-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-41-9-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-41-9-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-41-9-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-41-9-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-41-9-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-41-9-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-41-9-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB7-41-9-1.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.