



LSI
Logistics
Software
International

**Logistics Solutions Provider
to
Supply Chain Management**



Mobility Solutions
ISV/Software Solutions
Business Process and Integration

Suite 9.2, Level 1
Zenith Business Centre
6 Reliance Drive
Tuggerah NSW 2259
Australia
Tel: +61 2 4351 3500
Email: support@lsi.net.au
Web site: www.lsi.net.au
ABN: 33 414 337 680

iSupply software application - release advice - version 7.31.2.8

Prerequisites - iSupply

iSupply version 7.31.2.7
Microsoft .NET Framework 4.0
Microsoft Report Viewer 2010 SP1
SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 7.31.2.8
Release status: General release
Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 7.31.2.8

released 12/05/2009 (015748)

MSI path and name:

<http://www.lsi.net.au/files/versions/iSupply-7-31-2-8.zip>

SQL update scripts:

DB7-31-2-8.sql

Release inclusions and notes

Job-no	Code	Details/remarks
015674	DH	Consignment details entry – freight label allocation – rectify number allocation over specified last number in number range
015707	DH	Export consignment data to transporter – Mainfreight – revise export file to specification 2.8
015719	DH	Consignment details entry – rectify expected delivery date error when changing a forward dated consignment
015733	DH	Consignment details entry – improve consignment enquiry performance
015739	DH	Export consignment note details – EXL550P - rectify incorrect output of revenue kilograms
015747	DH	Export consignment data to transporter – TNT – change encoding to ANSI and remove BOM from export file
015747	DH	Export consignment data to transporter – Toll Priority – change encoding to ANSI and remove BOM from export file
015753	DH	Import freight tracking details from transporter – AaE – improve import performance
015753	DH	Import freight tracking details from transporter – AaE – exclude transporter code from consignment number match
015756	DH	Export consignment data to transporter – Mainfreight – rectify incorrect encoding node
015758	DH	Create/modify user accounts – improve display of permitted senders
015759	DH	Import freight tracking details from transporter – DHL – change date format to be consistent with all other freight tracking imports
015761	DH	Export consignment note details – EXL550P - rectify zeroed delivery cost
015765	DH	Export consignment data to transporter – AaE - AAE620P2 – include swap out consignments in export file
015768	DH	Export consignment data to transporter – Mainfreight - MRT620P – rectify missing consignments when multiple transporter accounts are present
015769	DH	Monitor scheduled tasks – rectify incorrect recording of export file names
015770	DH	Sender/warehouse details maintenance – rectify incorrect validation in change mode
015773	DH	Import consignment note details – MHN790P – rectify incorrect references recording

New maintainable settings

Setting	Details
None	None

<u>Import/export file format changes</u>	
Transaction	Data fields
None	None

Transaction	Data fields
None	None

<u>Notes</u>
None

iSupply install steps for this release when upgrading from iSupply version 7.31.2.7

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-31-2-8.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-31-2-8.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-31-2-8 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-31-2-8 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client\").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client\").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-31-2-8.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-31-2-8.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-31-2-8 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-31-2-8 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB7-31-2-8.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.