



LSI

**Logistics  
Software  
International**

## Logistics Solutions Provider to Supply Chain Management

**Microsoft**  
GOLD CERTIFIED  
Partner

Mobility Solutions  
ISV/Software Solutions  
Business Process and Integration

Suite 9.2, Level 1  
Zenith Business Centre  
6 Reliance Drive  
Tuggerah NSW 2259  
Australia  
Tel: +61 2 4351 3500  
Email: [support@lsi.net.au](mailto:support@lsi.net.au)  
Web site: [www.lsi.net.au](http://www.lsi.net.au)  
ABN: 33 414 337 680

### iSupply software application - release advice - version 9.7.1.1

#### **Prerequisites - iSupply**

iSupply version 9.6.1.1  
Microsoft .NET Framework 4.0  
Microsoft Report Viewer 2010 SP1  
SAP Crystal Reports Runtime Engine for .NET Framework 4

#### **Prerequisites - iSupplyRF**

Microsoft .NET Compact Framework 3.5

#### **iSupply release and version details**

iSupply version: 9.7.1.1  
Release status: General release  
Applications released: iSupply, iSupplyWeb, iSupplyRF

**This release must be installed to the test environment and user acceptance tested before installation to the live environment**

#### **iSupply version 9.7.1.1**

**released 03/05/2016 (019814)**

#### **MSI path and name:**

**<http://www.lsi.net.au/files/versions/iSupply-9-7-1-1.zip>**

#### **SQL update scripts:**

**DB9-7-1-1.sql**

#### **Release inclusions and notes**

Job-no	Code	Details/remarks
019811	LS	RF Receiving Modify RF receiving to hide expected count per the User setting on all listings iSupplyRF
019815	LS	Freight Tracking Improve freight tracking processes and enquiries iSupply, iSupplyWeb
019816	PC	RF Task Allocation Improve RF Task allocation processes iSupply
019817	SC	RF Task Monitor - RF Put Away task Stop the closure of all RF Put Away tasks upon deletion of a Shipment Advice iSupply
019818	LS	RF Task Monitor - performance Enhance the performance of the RF Task Monitor refresh process iSupply
019819	PC	Export Consignment Data to Transporter Adjust consignment number in electronic export format iSupply
019826	PC	Freight Label Print Strip characters not compatible with zebra 2D barcode printing (e.g. comma) iSupply, iSupplyWeb
019832	SC	Cycle Count - Add Unexpected Product Modify Cycle Count completion process to allow entry of Unexpected Products iSupply
019833	PM	SSCC Label Printing - Myer Adjust labels per Myer specification iSupply

#### **New maintainable settings**

Setting	Details
Transporter Details	Tracking type
Transporter Details	DIFOT calculation
Transporter Details	Pick up time

#### **Import/export file format changes**

Transaction	Data fields
None	None

**Notes**

None

## **iSupply install steps for this release when upgrading from iSupply version 9.6.1.1**

### **Preparation**

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

### **Application server (x86)**

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 9-7-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 9-7-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

### **Application server (x64)**

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 9-7-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 9-7-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
  - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client\").
  - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
  - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client\").
  - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

### **Web server (x86)**

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 9-7-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 9-7-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

### **Web server (x64)**

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 9-7-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 9-7-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

### **Database server**

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB9-7-1-1.sql.

### **Finalisation**

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.