



**LSI**  
Logistics  
Software  
International

Logistics Solutions Provider  
to  
Supply Chain Management



Mobility Solutions  
ISV/Software Solutions  
Business Process and Integration

Suite 9.2, Level 1  
Zenith Business Centre  
6 Reliance Drive  
Tuggerah NSW 2259  
Australia  
Tel: +61 2 4351 3500  
Email: [support@lsi.net.au](mailto:support@lsi.net.au)  
Web site: [www.lsi.net.au](http://www.lsi.net.au)  
ABN: 33 414 337 680

### **iSupply software application - release advice - version 7.38.1.1**

#### **Prerequisites - iSupply**

iSupply version 7.37.3.1  
Microsoft .NET Framework 4.0  
Microsoft Report Viewer 2010 SP1  
SAP Crystal Reports Runtime Engine for .NET Framework 4

#### **Prerequisites - iSupplyRF**

Microsoft .NET Compact Framework 3.5

#### **iSupply release and version details**

iSupply version: 7.38.1.1  
Release status: General release  
Applications released: iSupply, iSupplyWeb, iSupplyRF

**This release must be installed to the test environment and user acceptance tested before installation to the live environment**

**iSupply version 7.38.1.1** released 30/09/2009 (016171)

**MSI path and name:** <http://www.lsi.net.au/files/versions/iSupply-7-38-1-1.zip>

**SQL update scripts:** DB7-38-1-1.sql

#### **Release inclusions and notes**

Job-no	Code	Details/remarks
--------	------	-----------------

016012	DH	Create AASN - rectify the creation of multiple AASN's for one consignment
016101	HW	Import pick slips - Prism - bypass the automatic update of product cubic metres and kilograms
016110	DH	Import consignment details - Covidien - include enhanced transporter selection determination for importing consignments
016147	DH	Print freight label - AaE - Barcode Blaster and Zebra printers - include sender telephone number in freight label data
016150	DH	Export consignment details to transporter - Startrack - adjust the construction of the external export file name
016157	AI	Export consignment details to transporter - Booth Transport - add consignment export and tracking import
016172	LS	iSupplyRF cycle count - refactor current light version and include in iSupplyRF application suite
016183	DH	Consignment details entry / update / enquiry - rectify the setting of the default transporter code and default service code by receiver
016185	LS	Pallet transfer report - improve data capture and reporting functionality
016191	LS	Export consignment details to transporter - Courier Australia - remove from iSupply
016219	HW	Order entry / enquiry - rectify the updating of receiver details when changing an opened order
016221	UT	Transporter details maintenance - ensure that the transporter code is always upper case
016223	DH	Consignment details entry / update / enquiry - rectify allocation of head port on returns PDF labels
016241	YM	Export sales orders with consignment details - rectify incorrect export file creation on subsequent export from already exported data
016253	IG	Scan and pack orders - rectify non-printing of SSCC labels for release blanket orders
		<b>Incorporations from fix versions</b>
		<b>From version 7.33.2.7</b>
016133	CA	Scan and pack orders - single unit pack - rectify incorrect pack quantities when the user cancelled the pack
016160	CA	Picking/packing preparation - rectify order quantity on the report when a product occurs more than once in a store
016202	YM	Case scanning - rectify pack unit and sales order status processing when the consignment is cancelled
016203	YM	Transporter details maintenance - ET program - assume "Generic" if left blank
016206	CA	Import consignment note details - Masterpack - rectify consignment consolidation and recording of references
016213	YM	Export consignment details to transporter - Toll Priority - adjust export format
016218	YM	Services maintenance - allow "Label at entry" when "Prepaid"
		<b>From version 7.33.2.8</b>
016233	YM	Export Sales Orders with Consignment Details - GFast - ensure orders output all scanned cases
		<b>From version 7.37.2.5</b>
016201	DH	Export consignment data to transporter - AAE (manifest) - reduce time taken and impact on system when running

### **New maintainable settings**

<b>Setting</b>	<b>Details</b>
Services	Service type
Transporter Selection Details	Pack-unit-type
Transporter Selection Details	Service-type

### **Import/export file format changes**

<b>Transaction</b>	<b>Data fields</b>
None	None

### **Notes**

None

## **iSupply install steps for this release when upgrading from iSupply version 7.37.3.1**

### **Preparation**

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

### **Application server (x86)**

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-38-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-38-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

### **Application server (x64)**

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-38-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-38-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
  - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
  - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
  - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
  - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

### **Web server (x86)**

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-38-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-38-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

### **Web server (x64)**

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-38-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-38-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

### **Database server**

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB7-38-1-1.sql.

### **Finalisation**

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.