



LSI
Logistics
Software
International

**Logistics Solutions Provider
to
Supply Chain Management**



Mobility Solutions
ISV/Software Solutions
Business Process and Integration

Suite 9.2, Level 1
Zenith Business Centre
6 Reliance Drive
Tuggerah NSW 2259
Australia
Tel: +61 2 4351 3500
Email: support@lsi.net.au
Web site: www.lsi.net.au
ABN: 33 414 337 680

iSupply software application - release advice - version 9.6.1.1

Prerequisites - iSupply

iSupply version 9.5.1.1
Microsoft .NET Framework 4.0
Microsoft Report Viewer 2010 SP1
SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 9.6.1.1
Release status: General release
Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 9.6.1.1

released 17/03/2016 (019805)

MSI path and name:

<http://www.lsi.net.au/files/versions/iSupply-9-6-1-1.zip>

SQL update scripts:

DB9-6-1-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks
019760	AI	Import Freight Tracking - BOO785P Rectify event description display iSupply
019785	AI	Import Invoices - new format BOOTH Add invoice import format for BOOTHs iSupply
019794	VA	Freight Label Print - iSupplyWeb Remove freight label print limit from iSupplyWeb iSupplyWeb
019804	LS	Consignment Entry Enquiry Rectify exception error around transporter service selection iSupply
019806	LS	Freight Label Print - Star Track 8.6 Rectify printing of 2D barcodes when generated from browser iSupplyWeb
019807	PC	Freight Label Print - Direct Freight Express Modify label spacing around items on the DFE freight label iSupply, iSupplyWeb
019808	PM	Stock Enquiry - iSupply Web Portal Rectify error when drilling into stock enquiry (Portal only) iSupplyPortal
019812	GP	Allocate Locations to Charging Zones - DAT200P Enhance performance and locking when retrieving head port from Tempo iSupply

New maintainable settings

Setting	Details
None	None

Import/export file format changes

Transaction	Data fields
None	None

Notes

None

iSupply install steps for this release when upgrading from iSupply version 9.5.1.1

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 9-6-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 9-6-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 9-6-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 9-6-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 9-6-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 9-6-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 9-6-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 9-6-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB9-6-1-1.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.