



Logistics Solutions Provider to Supply Chain Management



Mobility Solutions ISV/Software Solutions Business Process and Integration Suite 9.2, Level 1
Zenith Business Centre
6 Reliance Drive
Tuggerah NSW 2259
Australia
Tel: +61 2 4351 3500
nail: support@lsi.net.au

Email: support@lsi.net.au Web site: www.lsi.net.au ABN: 33 414 337 680

iSupply software application - release advice - version 9.83.1.1

Prerequisites - iSupply

Prerequisites - iSupplyRF

iSupply version 9.82.1.1

Microsoft .NET Compact Framework 3.5

Microsoft .NET Framework 4.0 Microsoft Report Viewer 2010 SP1

SAP Crystal Reports Runtime Engine for .NET Framework 4

iSupply release and version details

iSupply version: 9.83.1.1 Release status: General release

Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before

installation to the live environment

iSupply version 9.83.1.1 released 18/02/2025 (022534)

MSI path and name: http://www.lsi.net.au/files/versions/iSupply-9-83-1-1.zip

SQL update scripts: DB9-83-1-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks	
022529	AZ	Pick sequencing Add ability to sequence picking route by a product's static primary location iSupply, iSupplyRF, iSupplyPortable	
022535	KS	Consignment Entry Use Receiver masterfile shipping instructions when not provided in order iSupply	
022536	KS	Order progress Rectify status display for orders that are despatched with AASN iSupply	
022537	KS	Consignment Entry Limit pick slip references to one per order on consignments iSupply	
022538	KS	RF Task Monitor Add support for multiple columns (Hold Shift key to select multiple columns) iSupply	
022540	KS	RF Task Monitor Use order details rather than Receiver masterfile (Ship-to) iSupply	
022541	KS	Order closure process Process store closures when a store has zero product quantity allocated iSupply, iSupplyWebServices, iSupplyRF	
		Incorporations from fix versions	
		From version 9.73.2.1	
022498	CA	Import Freight Tracking Details from Transporter - AUP785P Updates to latest Australia Post/Star Track tracking specifications eCS, iSupply	
022500	LS	Transporter Settings - Phone Validation Update telephone number libraries to latest validation eCS, iSupply, iSupplyWeb, iSupplyRESTServices	
022514	CA	Export Consignment Data to Transporter - STE620P Map consignment reference lines to STE item reference iSupply, eCS	

New maintainable settings

Setting	Details
	Use product primary for pick sequence
	_

Import/export file format changes

7	Transaction	Data fields

None	None
Notes None	

Supply install steps for this release when upgrading from iSupply version 9.82.1.1

Preparation

- 1. Ensure all users are logged out of iSupply and cannot log in.
- 2. Stop the eCS service on the server that runs it.
- 3. Stop any external processes that may access the iSupply database.
- 4. Make a backup copy of the iSupply SQL database.

Application server (x86)

- 1. Uninstall the currently installed iSupply Windows version via Control Panel.
- 2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
- 3. Install iSupply Windows 9-83-1-1.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
- 5. Install iSupply eCS Service 9-83-1-1.msi by running "setup.exe".
- 6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service \iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

- 1. Uninstall the currently installed iSupply Windows version via Control Panel.
- 2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
- 3. Install iSupply Windows 9-83-1-1 x64.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
- 5. Install iSupply eCS Service 9-83-1-1 x64.msi by running "setup.exe".
- 6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service \iSupplyeCSService.exe.config" has been updated with the server and database names.
- 7. NGEN iSupply Windows
- 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client\").
- 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
- 8. NGEN iSupply eCS Service
- 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client\").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

- 1. Uninstall the currently installed iSupply Web Services version via Control Panel.
- 2. Uninstall the currently installed iSupply Web version via Control Panel.
- 3. Install iSupply Web Services 9-83-1-1.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
- 5. Install iSupply Web 9-83-1-1.msi by running "setup.exe".
- $6. \ Ensure \ that \ the \ configuration \ file \ "C:\inetpub\wwwroot\iSupplyWeb\web.config" \ has \ been \ updated \ with \ the \ URL \ of \ the \ iSupplyWebServices.$

Web server (x64)

- 1. Uninstall the currently installed iSupply Web Services version via Control Panel.
- 2. Uninstall the currently installed iSupply Web version via Control Panel.
- 3. Install iSupply Web Services 9-83-1-1 x64.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
- 5. Install iSupply Web 9-83-1-1 x64.msi by running "setup.exe".
- 6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB9-83-1-1.sql.

Finalisation

- 1. Test run iSupply.
- 2. Start the eCS service on the server that runs it.
- 3. Start any external processes that may access the iSupply database.
- 4. Allow users to login to iSupply.