



LSI
 Logistics
 Software
 International

**Logistics Solutions Provider
 to
 Supply Chain Management**



Mobility Solutions
 ISV/Software Solutions
 Business Process and Integration

Suite 9.2, Level 1
 Zenith Business Centre
 6 Reliance Drive
 Tuggerah NSW 2259
 Australia
 Tel: +61 2 4351 3500
 Email: support@lsi.net.au
 Web site: www.lsi.net.au
 ABN: 33 414 337 680

iSupply software application - release advice - version 8.23.1.1

Prerequisites - iSupply

iSupply version 8.22.1.1
 Microsoft .NET Framework 4.0
 Microsoft Report Viewer 2010 SP1
 SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 8.23.1.1
 Release status: General release
 Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 8.23.1.1

released 16/06/2014 (018982)

MSI path and name:

<http://www.lsi.net.au/files/versions/iSupply-8-23-1-1.zip>

SQL update scripts:

DB8-23-1-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks
018786	SC	Shipment Advice Receiving - Auto Receive Delivery Advice Stage 1 of Auto Receiving Supplier Delivery Advices iSupply, iSupplyPortal [TD6]
018927	TA	Consignment Details Entry - Consignment Number Allocation Fix consignment prefix allocation iSupply, iSupplyWeb [TD8] (NHU)
018986	AU	Export Consignment Data to Transporter - Tamex Include cubic dimensions in Tamex consignment export file iSupply, iSupplyWeb [TD8] (NHU)
018993	SL	Export Consignment Data to Transporter - AirRoad Update AirRoad export files to latest AirRoad specification iSupply, iSupplyWeb [TD8] (NHU)
018995	PM	RF Receiving Scan Product - Error when receiving product Error when receiving for a sender that is different than the users default sender iSupply RF [TD2]
018997	DA	Freight Label Print - Toll Priority Ensure the correct transporter account is printed on freight label iSupply, iSupplyWeb [TD8] (NHU)
018999	SC	Print Interim Box Numbers Prevent duplicate IBN numbers with concurrent users iSupply [TD6] (NHU)
019003	PM	RF Pick Standardise order number maximum length across databases iSupply [TD8] (NHU)
019004	LS	RF Task Monitor - Search Filter Allow non-numeric characters in document search iSupply [TD8] (NHU)
019011	PC	Despatch Orders - Consignment Details Entry Ensure the width column is selected when tabing between columns iSupply [TD2]
019014	LS	Configuration file - Include SuppressBOMCharacters for additional interfaces Include the suppressbomCharacters config attribute for iSupply windows and ecs iSupply, ECS [TD2]
019017	AU	Consignment Note Entry - Consignment Number Toll IPEC Fix consignment number construction for Toll IPEC (leading zeros) iSupply, iSupplyWeb [TD2]
019026	PC	Export Consignment Data to Transporter - COPE Differentiate pallets and cartons in export file iSupply, iSupplyWeb [TD8]

<u>New maintainable settings</u>	
Setting	Details
	Delivery advice header Id
	Delivery advice number
	Shipment advice number
	Date delivered
	Cnote number
	Container number
	Date invoiced
	Invoice number
	Landed product cost ex GST
	Landed other cost ex GST
	Landed cost total GST
	Landed cost total inc GST
	Shipment advice header record Id
	SSCC number
	Company product Id
	EAN code
	Product description
	Batch number
	Expiry date
	Quantity ordered
	Quantity supplied
	Product cost unit
	Product cost total
	Percentage GST
	Delivery advice header id
	Delivery advice line Id
	Delivery advice serial Id
	Serial number
	Shipment advice line Id
	Sender warehouse Id
	Supplier Id
	Unit of measure Id
	Quantity back ordered
	Line Id
	Status
<u>Import/export file format changes</u>	
Transaction	Data fields
None	None
<u>Notes</u>	
None	

iSupply install steps for this release when upgrading from iSupply version 8.22.1.1

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 8-23-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 8-23-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 8-23-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 8-23-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 8-23-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 8-23-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 8-23-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 8-23-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB8-23-1-1.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.