



LSI
 Logistics
 Software
 International

**Logistics Solutions Provider
 to
 Supply Chain Management**



Mobility Solutions
 ISV/Software Solutions
 Business Process and Integration

Suite 9.2, Level 1
 Zenith Business Centre
 6 Reliance Drive
 Tuggerah NSW 2259
 Australia
 Tel: +61 2 4351 3500
 Email: support@lsi.net.au
 Web site: www.lsi.net.au
 ABN: 33 414 337 680

iSupply software application - release advice - version 7.41.2.1

Prerequisites - iSupply

iSupply version 7.41.1.1
 Microsoft .NET Framework 4.0
 Microsoft Report Viewer 2010 SP1
 SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 7.41.2.1
 Release status: General release
 Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 7.41.2.1

released 15/01/2010 (016498)

MSI path and name:

<http://www.lsi.net.au/files/versions/iSupply-7-41-2-1.zip>

SQL update scripts:

DB7-41-2-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks
014672	LS	Order tracking report - include user-id in report data
015196	LS	Sender details maintenance - rectify system error when deleting a sender that is the default sender for a user
015845	LS	iSupply release install - send advising email to LSI support when a release is installed
016284	LS	Transporter rates maintenance - change/delete/enquire - include the origin code as search criteria to speed up the list population
016312	LS	Consignment details entry - improve the calculation of dangerous goods and fuel surcharges
016327	LS	Consignment details entry - rectify the auto-population of warehouse code when the sender code changes
016432	LS	Consignment details entry - reverse origin and destination codes for swap out consignments
016462	DH	Export Consignment Data to Transporter - AAE - output correct zone codes in Zone, Sticker, Zone To and Zone From fields when the consignment is a return
016474	DH	Import Freight Tracking Details from Transporter - Mainfreight - redesign to be consistent with other freight tracking imports
016484	DH	Scheduled Task Log Report - rectify system crash when displaying report
016499	LS	Despatched Consignments Report - refactor into business logic layer
016500	DH	Export Consignment Data to Transporter - ensure transporter dropdown does not duplicate transporter codes
016502	DH	Consignment Details Entry / Update / Enquiry - prevent carriage returns being data entered into the references grid
016507	GM	Scan and pack orders - rectify system error when retrieving in excess of 700 SSCCs
016508	PC	Import pick slips - Jiwa - refactor into standard pick slip import to optimise performance

New maintainable settings

Setting	Details
None	None

Import/export file format changes

Transaction	Data fields
None	None

Notes

None

iSupply install steps for this release when upgrading from iSupply version 7.41.1.1

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-41-2-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-41-2-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-41-2-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-41-2-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-41-2-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-41-2-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-41-2-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-41-2-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB7-41-2-1.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.