



LSI
Logistics
Software
International

Logistics Solutions Provider
to
Supply Chain Management



Mobility Solutions
ISV/Software Solutions
Business Process and Integration

Suite 9.2, Level 1
Zenith Business Centre
6 Reliance Drive
Tuggerah NSW 2259
Australia
Tel: +61 2 4351 3500
Email: support@lsi.net.au
Web site: www.lsi.net.au
ABN: 33 414 337 680

iSupply software application - release advice - version 7.58.1.1

Prerequisites - iSupply

iSupply version 7.57.10.1
Microsoft .NET Framework 4.0
Microsoft Report Viewer 2010 SP1
SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 7.58.1.1
Release status: General release
Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 7.58.1.1 released 22/11/2011 (017759)

MSI path and name: <http://www.lsi.net.au/files/versions/iSupply-7-58-1-1.zip>

SQL update scripts: DB7-58-1-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks
--------	------	-----------------

015867	LS	Export Pick Slips Ensure that the pick slip exports writes an export event to the order event log iSupply
015870	LS	Export Orders - Great Plains Ensure that the order exports writes an export event to the order event log iSupply
015888	LS	Receiver Details Maintenance Remove setting PRINT PACK SLIP ON DESPATCH iSupply
016867	LS	Set Up Scheduled Tasks Remove Database Details frame and content iSupply
017043	LS	Maintenance forms Imrpove consistency of shortcut keys iSupply
017211	PC	iSupply RF applications Improve network connection drop out procedures iSupplyRF
017245	PC	RF Task Monitor Include additional data fields (Ship-to, Date-created) iSupply
017270	HA	Export Consignment Data to Transporter Rectify missing account code in export file - Toll Ipec iSupply
017330	PC	iSupplyRF applications Allow login with upper and lower case user ids iSupplyRF
017358	RC	Import Pick Slips - Great Plains Improve handling of email address in importing pick slip file iSupply
017469	LS	Build Manifests Rectify system error when preparing manifest report iSupplyWeb
017556	LS	iSupply applications Improve CTRL+C copy key function iSupply
017570	LS	RF Task Monitor Improve the setting of a task status when the task is resumed iSupply
017630	LS	Pick/Pack Improve processing when Sender/Warehouse ACCEPT PACK UNIT is checked iSupplyRF
017654	PC	Export Pick Slips Rectify intermittent loss of freight charge data iSupply
017707	LS	iSupplyRF applications Improve licence warning messages on login iSupplyRF
017751	PC	Pick/Pack Display current interim box number iSupplyRF
017754	LS	RF Task Monitor Include additional data fields in task monitor grid (State, Supplier, Products, Cubic, Kilograms) iSupply
		Incorporations from fix versions
		From version 7.41.8.5
017535	UT	Consignment Details Entry Changes to freight label creation to print state and postcode correctly iSupply

New maintainable settings

Setting	Details
Sender Details	Driver Import
Sender Details	Driver Export

Import/export file format changes

Transaction	Data fields
None	None

Notes

None

iSupply install steps for this release when upgrading from iSupply version 7.57.10.1

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-58-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-58-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-58-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-58-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-58-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-58-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-58-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-58-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB7-58-1-1.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.